

# API

## Tip

If you are having a hard time, you can always have a look at the examples page where the classes, methods and parameters are used in practice.

## WebMethod

```
class edurov.core.WebMethod(index_file, video_resolution='1024x768', fps=30, server_port=8000, debug=False, runtime_functions=None, custom_response=None)
```

[\[source\]](#) 

Starts a video streaming from the raspberry pi and a webserver that can handle user input and other requests.

### Parameters:

- **index\_file** (*str*) – Absolute path to the frontpage of the webpage, must be called `index.html`. For more information, see [Displaying the video feed](#).
- **video\_resolution** (*str, optional*) – A string representation of the wanted video resolution in the format WIDTHxHEIGHT.
- **fps** (*int, optional*) – Wanted framerate, may not be achieved depending on available resources and network.
- **server\_port** (*int, optional*) – The web page will be served at this port
- **debug** (*bool, optional*) – If set True, additional information will be printed for debug purposes.
- **runtime\_functions** (*callable or list, optional*) – Should be a callable function or a list of callable functions, will be started as independent processes automatically. For more information, see [Controlling motors \(or anything\)](#).
- **custom\_response** (*callable, optional*) – If set, this function will be called if default web server is not able to handle a GET request, should return a str or None. If returned value starts with `redirect=` followed by a path, the server will redirect the browser to this path. The callable must accept two parameters whereas the second one is the requested path. For more information, see [Custom responses](#).

## Examples

```
>>> import os
>>> from edurov import WebMethod
>>>
>>> file = os.path.join(os.path.dirname(__file__), 'index.html', )
>>> web_method = WebMethod(index_file=file)
>>> web_method.serve()
```

**serve(*timeout=None*)** [\[source\]](#)

Will start serving the web page defined by the `index_file` parameter

**Parameters:** `timeout` (*int, optional*) – if set, the web page will only be served for that many seconds before it automatically shuts down

### Notes

This method will block the rest of the script.

## ROVSyncer

**class** `edurov.sync.ROVSyncer` [\[source\]](#)

Holds all variables for ROV related to control and sensors

### Examples

```
>>> import Pyro4
>>>
>>> with Pyro4.Proxy("PYRONAME:ROVSyncer") as rov:
>>>     while rov.run:
>>>         print('The ROV is still running')
```

**actuator**

Dictionary holding actuator values

**Getter:** Returns actuator values as dict

**Setter:** Update actuator values with dict

**Type:** dict

**run**

Bool describing if the ROV is still running

**Getter:** Returns bool describing if the ROV is running

**Setter:** Set to False if the ROV should stop

**Type:** bool

### sensor

Dictionary holding sensor values

**Getter:** Returns sensor values as dict

**Setter:** Update sensor values with dict

**Type:** dict

## KeyManager

`class edurov.sync.KeyManager` [\[source\]](#)

Keeps control of all user input from keyboard.

### Examples

```
>>> import Pyro4
>>>
>>> with Pyro4.Proxy("PYRONAME:KeyManager") as keys:
>>> with Pyro4.Proxy("PYRONAME:ROVSyncer") as rov:
>>>     keys.set_mode(key='l', mode='toggle')
>>>     while rov.run:
>>>         if keys.state('up arrow'):
>>>             print('You are pressing the up arrow')
>>>         if keys.state('l'):
>>>             print('light on')
>>>         else:
>>>             print('light off')
```

### Note

When using the methods below a **key identifier** must be used. Either the keycode (int) or the KeyASCII or Common Name (str) from the table further down on this page can be used. Using keycode is faster.

### arrow\_dict

Dictionary with the state of the keys *up arrow*, *down arrow*, *left arrow* and *right arrow*

`keydown(key, make_exception=False)` [\[source\]](#)

Call to simulate a keydown event

- Parameters:
- **key** (*int* or *str*) – key identifier as described above
  - **make\_exception** (*bool*, *optional*) – As default an exception is raised if the key is not found, this behavior can be changed by setting it to *False*

**keyup(key, make\_exception=False)** [\[source\]](#)

Call to simulate a keyup event

- Parameters:
- **key** (*int* or *str*) – key identifier as described above
  - **make\_exception** (*bool*, *optional*) – As default an exception is raised if the key is not found, this behavior can be changed by setting it to *False*

**qweasd\_dict**

Dictionary with the state of the letters q, w, e, a, s and d

**set(key, state)** [\[source\]](#)

Set the state of the key to True or False

- Parameters:
- **key** (*int* or *str*) – key identifier as described above
  - **state** (*bool*) – *True* or *False*

**set\_mode(key, mode)** [\[source\]](#)

Set the press mode for the key to *hold* or *toggle*

- Parameters:
- **key** (*int* or *str*) – key identifier as described above
  - **mode** (*str*) – *hold* or *toggle*

**state(key)** [\[source\]](#)

Returns the state of *key*

Parameters: **key** (*int* or *str*) – key identifier as described above

Returns: **state** – *True* or *False*

Return type: *bool*

## Keys table

Key	ASCII	Common Name	Keycode
K_BACKSPACE	\b	backspace	8
K_TAB	\t	tab	9
K_CLEAR		clear	
K_RETURN	\r	return	13
K_PAUSE		pause	
K_ESCAPE	^[	escape	27
K_SPACE		space	32
K_EXCLAIM	!	exclaim	
K_QUOTEDBL	"	quotedbl	
K_HASH	#	hash	
K_DOLLAR	\$	dollar	
K_AMPERSAND	&	ampersand	
K_QUOTE		quote	
K_LEFTPAREN	(	left parenthesis	
K_RIGHTPAREN	)	right parenthesis	
K_ASTERISK	*	asterisk	
K_PLUS	+	plus sign	
K_COMMA	,	comma	
K_MINUS	-	minus sign	
K_PERIOD	.	period	
K_SLASH	/	forward slash	
K_0	0	0	48
K_1	1	1	49
K_2	2	2	50
K_3	3	3	51
K_4	4	4	52
K_5	5	5	53
K_6	6	6	54
K_7	7	7	55
K_8	8	8	56
K_9	9	9	57
K_COLON	:	colon	
K_SEMICOLON	;	semicolon	
K_LESS	<	less-than sign	
K_EQUALS	=	equals sign	
K_GREATER	>	greater-than sign	
K_QUESTION	?	question mark	
K_AT	@	at	
K_LEFTBRACKET	[	left bracket	
K_BACKSLASH	\	backslash	
K_RIGHTBRACKET	]	right bracket	
K_CARET	^	caret	
K_UNDERSCORE	_	underscore	
K_BACKQUOTE	`	grave	
K_a	a	a	65
K_b	b	b	66
K_c	c	c	67
K_d	d	d	68
K_e	e	e	69
K_f	f	f	70
K_g	g	g	71
K_h	h	h	72
K_i	i	i	73
K_j	j	j	74
K_k	k	k	75
K_l	l	l	76
K_m	m	m	77
K_n	n	n	78
K_o	o	o	79
K_p	p	p	80
K_q	q	q	81
K_r	r	r	82
K_s	s	s	83
K_t	t	t	84
K_u	u	u	85
K_v	v	v	86
K_w	w	w	87
K_x	x	x	88

K_y	y	y	89
K_z	z	z	90
K_DELETE		delete	
K_KP0		keypad 0	
K_KP1		keypad 1	
K_KP2		keypad 2	
K_KP3		keypad 3	
K_KP4		keypad 4	
K_KP5		keypad 5	
K_KP6		keypad 6	
K_KP7		keypad 7	
K_KP8		keypad 8	
K_KP9		keypad 9	
K_KP_PERIOD	.	keypad period	
K_KP_DIVIDE	/	keypad divide	
K_KP_MULTIPLY	*	keypad multiply	
K_KP_MINUS	-	keypad minus	
K_KP_PLUS	+	keypad plus	
K_KP_ENTER	\r	keypad enter	
K_KP_EQUALS	=	keypad equals	
K_UP		up arrow	38
K_DOWN		down arrow	40
K_RIGHT		right arrow	39
K_LEFT		left arrow	37
K_INSERT		insert	45
K_HOME		home	36
K_END		end	35
K_PAGEUP		page up	33
K_PAGEDOWN		page down	34
K_F1		F1	
K_F2		F2	
K_F3		F3	
K_F4		F4	
K_F5		F5	
K_F6		F6	
K_F7		F7	
K_F8		F8	
K_F9		F9	
K_F10		F10	
K_F11		F11	
K_F12		F12	
K_F13		F13	
K_F14		F14	
K_F15		F15	
K_NUMLOCK		numlock	
K_CAPSLOCK		capslock	
K_SCROLLLOCK		scrolllock	
K_RSHIFT		right shift	
K_LSHIFT		left shift	
K_RCTRL		right control	
K_LCTRL		left control	
K_RALT		right alt	
K_LALT		left alt	
K_RMETA		right meta	
K_LMETA		left meta	
K_LSUPER		left Windows key	
K_RSUPER		right Windows key	
K_MODE		mode shift	
K_HELP		help	
K_PRINT		print screen	
K_SYSREQ		sysrq	
K_BREAK		break	
K_MENU		menu	
K_POWER		power	
K_EURO		Euro	

# Utilities

Different utility functions practical for ROV control

**edurov.utils.cpu\_temperature()** [\[source\]](#)

Checks and returns the on board CPU temperature

Returns:            **temperature** – the temperature

Return type:    **float**

**edurov.utils.free\_drive\_space(*as\_string=False*)** [\[source\]](#)

Checks and returns the remaining free drive space

Parameters:    **as\_string** (*bool, optional*) – set to True if you want the function to return a formatted string. 4278 -> 4.28 GB

Returns:            **space** – the remaining MB in float or as string if *as\_string=True*

Return type:    **float** or **str**

**edurov.utils.receive\_arduino(*serial\_connection*)** [\[source\]](#)

Returns a message received over *serial\_connection*

Expects that the message received starts with a 6 bytes long number describing the size of the remaining data. "0x000bhello there" -> "hello there".

Parameters:    **serial\_connection** (*object*) – the `serial.Serial` object you want to use for receiving

Returns:            **msg** – the message received or None

Return type:    **str** or None

**edurov.utils.receive\_arduino\_simple(*serial\_connection, min\_length=1*)** [\[source\]](#)

Returns a message received over *serial\_connection*

Same as `receive_arduino` but doesn't expect that the message starts with a hex number.

Parameters:

- **serial\_connection** (*object*) – the `serial.Serial` object you want to use for receiving
- **min\_length** (*int, optional*) – if you only want that the function to only return the string if it is at least this long.

Returns: `msg` – the message received or `None`

Return type: `str` or `None`

```
edurov.utils.send_arduino(msg, serial_connection) \[source\]
```

Send the *msg* over the *serial\_connection*

Adds a hexadecimal number of 6 bytes to the start of the message before sending it. "hello there" -> "0x000bhello there"

Parameters:

- `msg` (*str* or *bytes*) – the message you want to send
- `serial_connection` (*object*) – the `serial.Serial` object you want to use for sending

```
edurov.utils.send_arduino_simple(msg, serial_connection) \[source\]
```

Send the *msg* over the *serial\_connection*

Same as `send_arduino`, but doesn't add anything to the message before sending it.

Parameters:

- `msg` (*str* or *bytes*) – the message you want to send
- `serial_connection` (*object*) – the `serial.Serial` object you want to use for sending

```
edurov.utils.serial_connection(port='/dev/ttyACM0', baudrate=115200, timeout=0.05) \[source\]
```

Establishes a serial connection

Parameters:

- `port` (*str*, *optional*) – the serial port you want to use
- `baudrate` (*int*, *optional*) – the baudrate of the serial connection
- `timeout` (*float*, *optional*) – read timeout value

Returns: `connection` – a `serial.Serial` object if successful or `None` if not

Return type: `class` or `None`